# Mytana Viewer App Instructions - iOS



# 1 Install/Connect the App

- 1. Connect your phone or tablet to an internet source (Mytana Camera is not an internet source)
- 2. Open the App Store (iOS) or Play Store (Android) and search "Mytana Viewer"





3. Download Mytana Viewer App (you may need your phone password to install apps)



4. Make sure camera is OFF

Insert our Router in to one of the USB ports on the camera or control box



- 5. Power on the camera
- 6. On your phone/tablet Home Screen, go to Settings



- 7. Go to Wi-Fi settings
- 8. Select "Mytana - - " or "S4011" from the list of other networks that appears.

Note: This is not a wireless internet source, it iust establishes the connection to the camera so images can be seen.



## 2 Recording Video

Launch "Mytana Viewer" App Allow access if necessary







00:06 4. When finished

1. Press the "+" button

2. Name your Job and press "return" (iOS) or "Add" (Android)

Wait for connection 3. Press "Record" and activate microphone if voice-over is desired Press SNAPSHOT for single images

as needed

Wi-Fi

Device Network

CHOOSE A NETWORK...

Mytana - - - -

Ask to Join Networks

Local Network 3

÷ (i)

a → (i)

a ≈ (i)


recording, press "Stop"

Wait for job to process (finalize)

File will need to be exported, see next section.

# 3 Saving and Sharing Videos and Snapshots







3. From your device's Home screen, go to Settings and DISCONNECT from the MyTana WiFi signal. Return to data or a local WiFi network.



4. Open Photos to see saved snapshots or videos. Share images as you would any other photo or video.



www.MyTana.com

746 Selby Ave • St. Paul MN, 55104 fax: 651.222.1739

**Factory Direct Customer Service** M-F 7am - 5pm CST Competent • Polite • Clear

1.800.328.8170

# Mytana Viewer App



# **Instructions** – Android

# 1 Install/Connect the App

- 1. Connect your phone or tablet to an internet source (Mytana Camera is not an internet source)
- 2. Open the App Store (iOS) or Play Store (Android) and search "Mytana Viewer"





3. Download Mytana Viewer App (you may need your phone password to install apps)



4. Make sure camera is OFF

Insert our Router in to one of the USB ports on the camera or control box



- 5. Power on the camera
- 6. On your phone/tablet Home Screen, go to Settings
- 7. Go to Wi-Fi settings
- 8. Select "Mytana - or "S4011" from the list of other networks that appears.

Note: This is not a wireless internet source, it iust establishes the connection to the camera so images can

be seen.



#### **Recording Video**

**Launch "Mytana Viewer" App** Allow access if necessary







2. Name your Job and press "return"


Wait for connection



and activate microphone if voice-over is desired Press SNAPSHOT for single images as needed, not

while recording

3. Press "Record"



4. When finished recording, press "Stop" (job length is limited to 15 minutes)

Wait for job to process (finalize)

### **Sharing Videos and Snapshots**

After job is finalized (step 4 above), it will automatically be added to your device's Gallery.



1. From your device's Home screen, go to Settings and **DISCONNECT** from the MyTana WiFi signal. Return to data or a local WiFi network.



2. Open your Gallery to see saved snapshots or videos. Share as you would any other photo or video.



www.MyTana.com

746 Selby Ave • St. Paul MN, 55104 fax: 651.222.1739

1.800.328.8170

**Factory Direct Customer Service** M-F 7am - 5pm CST Competent • Polite • Clear